

# ScanRead

## Installation Instructions

- 1) Download the self-extracting file SCANREAD351.EXE.
- 2) Close all Windows programs.
- 3) Double-click on the SCANREAD351.EXE file and extract the contents to a folder on your hard drive.
- 4) Among the extracted files, you will find SETUP.EXE. Run SETUP.EXE. This starts the setup program for ScanRead.

## Additional Notes

Among the files extracted from SCANREAD351.EXE, you will find two files named README1.TXT and README2.TXT.

- README1.TXT will provide more information on ScanRead.
- README2.TXT will provide information on how to modify the FULLMENU.CNF file to add menu commands for analysis. The script for these analysis menu commands are also included in README2.TXT and they need to be extracted into a .OGS file. Please view README2.TXT for details.